


# Software Guide

## for Windows

- ZoomBrowser EX
- CameraWindow
- PhotoStitch

### Special Features

#### Transfer Images and Movies




#### Insert Text



#### Save Still Images From Movies



#### Edit Movies



#### Print Images



#### Back Up to a CD



#### Attach Images to Email



Plus many other useful features

# About this Manual

## Notation Conventions

The contents of this manual are classified according to the following symbols.

### ! IMPORTANT

- The “Important” sections contain operating precautions or important topics. Ensure that you read them.

### 💡 HINT

- The “Hint” sections contain procedural suggestions and tips for your convenience. Read them as necessary.


## Operating Environment

- This manual uses Windows Vista screen shots and procedures in the explanations. The screen shots and procedures may appear slightly different if you are using another version of Windows.
- The displayed screens and procedures may also differ slightly from the examples depending upon the camera or printer model in use.
- The explanations in this guide are based on the premise that a Canon compact digital camera will be used with the software.
- Some functions may not be available depending on the camera model.

## Word Searches

This document is provided as an Adobe Reader document. Use Adobe Reader’s Search functions to find specific words or phrases that you recall but cannot find. To access this function, in Adobe Reader click the [Edit] menu and select the [Search] option.

If you are using Adobe Reader 8 or later, you can also perform searches with the [Find] function right on the toolbar.



Input search text here

## Precautions for Connecting the Camera to the Computer

- When connecting the camera to the computer with an interface cable, make sure to connect the cable directly to the computer's USB port. The connection may not operate correctly if you attach the camera to the computer via a USB hub.
- The connection may not operate correctly if you are using other USB devices, excluding USB mice or keyboards, at the same time as the camera. If this occurs, disconnect the other devices from the computer and try reconnecting the camera.
- Do not connect two or more cameras at the same time to the same computer. The connections may not operate correctly.
- Do not allow the computer to go into sleep (standby) mode while a camera is connected via the USB interface cable. If this does happen, do not disconnect the interface cable. Try to awaken the computer with the camera in the connected state. Some computers will not awaken properly if you disconnect the camera while they are in sleep (standby) mode. Please refer to your computer manual for instructions regarding the sleep (standby) mode.
- Do not disconnect the camera from the computer if CameraWindow is displayed on the screen.

### **IMPORTANT**

- **You are recommended to use an AC adapter (sold separately) when connecting to a computer. Ensure that you use fully charged batteries if you cannot use an AC adapter.**
- **See the *Camera User Guide* for procedures on connecting the camera to the computer.**

# Table of Contents

About this Manual .....	2
Precautions for Connecting the Camera to the Computer .....	3
<b>Things to Remember .....</b>	<b>6</b>
<b>CameraWindow and ZoomBrowser EX .....</b>	<b>6</b>
CameraWindow and ZoomBrowser EX .....	6
<b>ZoomBrowser EX's Main Window .....</b>	<b>7</b>
How to Display the Main Window .....	7
Names of the Main Window Parts .....	7
<b>How to Perform Tasks .....</b>	<b>8</b>
Selecting Tasks and Task Window Procedures .....	8
<b>Mastering the Basics .....</b>	<b>9</b>
<b>Transferring Images .....</b>	<b>9</b>
Transferring Images by Connecting the Camera to a Computer .....	9
<b>Printing .....</b>	<b>12</b>
Printing a Single Image on a Single Page .....	12
Index Print .....	14
<b>How to Use CameraWindow .....</b>	<b>16</b>
First Menu Screen to Open .....	16
Image Transfer Screen .....	17
Organize Images Screen .....	18
<b>How to Use ZoomBrowser EX's Main Window .....</b>	<b>19</b>
Main Window .....	19
Display Modes .....	20
Display Control Panel .....	20
Browser Area Tasks .....	21
Properties Window .....	22
Viewer Window .....	23
<b>More Advanced Techniques .....</b>	<b>24</b>
<b>Editing Images .....</b>	<b>24</b>
Red Eye Correction .....	24
Auto Adjustment .....	24
Color/Brightness Adjustment .....	25
Adjusting Sharpness—Emphasizing Outlines .....	25
Trimming—Cropping a Portion of an Image .....	26
Inserting Text .....	26
Using Other Editing Software .....	27
Attaching Sounds .....	28
Creating Panoramic Images—PhotoStitch .....	29
Editing Movies .....	30
Converting RAW Images—Digital Photo Professional .....	31

<b>Exporting .....</b>	<b>33</b>
Changing Image (Stills) Sizes and Types .....	33
Changing Movie Sizes and Types .....	33
Extracting Stills from Movies.....	34
Exporting Shooting Information .....	34
Creating Computer Screen Saver Images .....	35
Creating Computer Wallpaper Images.....	35
Saving to CDs .....	36
<b>Uploading Movies to YouTube .....</b>	<b>37</b>
Uploading to YouTube .....	37
<b>Email.....</b>	<b>38</b>
Attaching Images to Email.....	38
<b>Slide Shows.....</b>	<b>39</b>
Viewing Images in Slide Shows.....	39
<b>Image Management.....</b>	<b>40</b>
Changing File Names in Batches .....	40
Sorting Images into Folders by Shooting Date .....	40
<b>Configuring Image Information Settings .....</b>	<b>41</b>
Setting Ratings.....	41
Inserting Comments.....	41
Assigning Keywords.....	42
<b>Searching, Filtering and Sorting Images.....</b>	<b>43</b>
Searching Images.....	43
Filtering Images .....	44
Sorting Images .....	44
<b>Comparing Images .....</b>	<b>45</b>
Comparing Multiple Images.....	45
<b>My Camera Settings.....</b>	<b>46</b>
Changing the Shutter Sound and Start-Up Image.....	46
<b>Transferring Images .....</b>	<b>48</b>
Transferring Images to a Camera.....	48
<b>CANON IMAGE GATEWAY .....</b>	<b>49</b>
About CANON iIMAGE GATEWAY (for U.S.A. customers only).....	49
Registering .....	49
Available Services.....	50
<b>Preference Settings .....</b>	<b>51</b>
Customizing ZoomBrowser EX.....	51
Customizing the Task Buttons.....	51
<b>Appendices .....</b>	<b>52</b>
List of Available Functions.....	52
Supported Image Types .....	54
Uninstalling the Software .....	55
Memory Card Folder Structure .....	56
Troubleshooting .....	57

# CameraWindow and ZoomBrowser EX

## CameraWindow and ZoomBrowser EX

The following two windows are the main ones used for CameraWindow and ZoomBrowser EX procedures.




### CameraWindow

This is software that communicates with the camera.

You can use it to transfer images to and from the camera, organize images on the camera, and upload movies on the camera to web services.

The menu screen at the right will appear when the camera is connected to a computer.



CameraWindow closes, and the screen changes after the images are transferred from the camera.





### ZoomBrowser EX

This is software that manages images transferred to a computer.

You can use it to view, edit and print images on a computer. If you close CameraWindow after transferring images, the window at the right will appear.

You can also open the window by double-clicking the icon on the desktop.



#### HINT

##### Use the Help Function

The  (Help) button or Help menu is available in most CameraWindow and ZoomBrowser EX windows. It is there for when you are unsure how to proceed.




# ZoomBrowser EX's Main Window

## How to Display the Main Window

ZoomBrowser EX's Main Window will appear after the camera images are transferred and CameraWindow closes. You can also display it by double-clicking the ZoomBrowser EX icon on the desktop.



## Names of the Main Window Parts



### Properties Icon (Displays Image Properties)

- : Image recorded using the camera's Stitch Assist mode
- : RAW image
- : Movie
- : Super Slow Motion Movie
- : Image with sound memo attached
- : Protected image
- : Image recorded using the camera's AEB function
- : Rotated image (rotated in display only)

### Browser Area

Icons that indicate image properties display around images, as shown on the left.

# How to Perform Tasks

## Selecting Tasks and Task Window Procedures

Many ZoomBrowser EX functions can be accessed by selecting a task in the Main Window and following the instructions in the guidance section of the new window. For further details on the functions, refer to ["List of Available Functions"](#) in the appendix.

### 1 Select a task.

The screenshot shows the ZoomBrowser EX Main Window and the Edit Image dialog box. The Main Window has a 'Tasks' panel on the left with a red box around it. A blue arrow points from the 'Edit Image' task to the Edit Image dialog box. The dialog box has a '1 Select Image' step, a '2 Select Editing Tool' step (highlighted with a red box), and a '3 Finish' step. A red box also highlights the 'Return to Main Menu' button. The 'Edit Settings' panel on the right shows various editing options like Red Eye Correction, Auto Adjustment, Color/Brightness Adjustment, Sharpness, Trim, Insert Text, and Edit with external image editor. A 'Manage List...' button is also visible. The 'Selected Items' list at the bottom shows 'IMG\_0001.JPG'.

The major steps for the task appear here. Follow the steps in order. You can return to a previous step.

An overview for the selected task appears here.

Use this task to correct photos of subjects with red-eye, adjust photos automatically, change the color balance or sharpness, trim the photo, insert text, or edit the photo with an external image editor.

Cancel the procedure and returns to the previous window.

### 2 Follow the instructions to perform the task.

# Transferring Images

## Transferring Images by Connecting the Camera to a Computer

Transfer the camera images to the computer.



### ! IMPORTANT

- The instructions in this software manual assume that you have correctly installed the software. See the *Camera User Guide* for software installation procedures.
- For details on how to connect the camera to a computer, refer to the *Camera User Guide*. Please also refer to [“Precautions for Connecting the Camera to the Computer”](#).
- With some versions of Microsoft Windows, CameraWindow may not open when the camera is connected. In this case, double-click the ZoomBrowser EX icon on the desktop to start ZoomBrowser EX and open the Main Window. Click the [Acquire & Camera Settings] task button, followed by [Connect to Camera].




**1** Connect the camera to the computer with the supplied interface cable.


**2** Turn on the camera power, set it to playback mode and prepare it to communicate with the computer.

**3** When a window similar to the one at the right appears, click [Downloads Images From Canon Camera using Canon CameraWindow].

With Windows XP, click [Canon CameraWindow] then [OK] in the AutoPlay window.

For Windows 7, use the following steps to display CameraWindow.

1. Click  on the task bar.
2. In the screen that appears, click the  link to modify the program.
3. Click [Downloads Images From Canon Camera using Canon CameraWindow], then click [OK].
4. Double click .



## 4

Click [Import Images from Camera], and then click [Import Untransferred Images].

Only images that have not yet been transferred will start to transfer.



After you click [OK] in the dialog that indicates the transfer is complete and close the CameraWindow screen, the transferred images will display in the Main Window.

You can select the newly transferred images by their shooting dates or My Category (select models only) classification.



: Folders containing newly acquired images


CameraWindow (Menu Screen)




- Images from memory cards with large numbers of images (more than 1,000) may not transfer correctly. If this happens, please use a memory card reader to transfer. For details on transferring images from a memory card reader, refer to ["Transferring Images Using a Memory Card Reader"](#).
- Movie files take time to transfer since the files are large.



### HINT

#### Changing the Transfer Destination Folder


The default settings save transferred images into the [Pictures] or [My Pictures] folders. To change the destination folder, click the  button shown on the right in Step 4 as described above, then click the [Import] button. In the [Folder Settings] tab, click [Browse] to complete settings in the screen currently displayed.

#### Changing the software that displays after images have been transferred

You can choose the software that displays after images have been transferred. Click  in the upper right corner of CameraWindow, then click [Import] in the screen that appears and choose the [After Import] tab. After making your settings, press [OK] and close the [Preferences] screen.




**HINT****Select Images to Import**

To transfer only a selection of images from the camera, click [Import Images from Camera] in CameraWindow (menu screen), [Select Images to Import], then select images in the image transfer screen, and click the  (Import) button. For details, refer to “Image Transfer Screen”.

**Import All Images**

To transfer all images on the camera, click [Import Images from Camera] in CameraWindow (menu screen) then, [Import All Images].

**Automatically Transferring Images on CameraWindow Start-Up**

To automatically transfer images when CameraWindow starts up, click the button shown on the right in CameraWindow (menu screen), then click the [Import] button, and the [Auto Import] tab. Add a checkmark to [Start importing images automatically when this software is launched.].

**Transferring Images Using a Memory Card Reader**

An action selection window will open when you insert a memory card into the memory card reader. If you select [View/Download Images Using Canon ZoomBrowser EX], ZoomBrowser EX will start and display the following window. Use this window to perform the transferring procedures.



Transfers all images that have not yet been transferred.

Allows you to select and transfer images.

Prints images.

Configures the transfer folder and other settings.


**! IMPORTANT**

- **Movies transferred with the Windows 7 transfer function may not be correctly processed in ZoomBrowser EX. Transfer the movies with the included software.**

# Printing

## Printing a Single Image on a Single Page

Prints one image per page.




### HINT


#### Printing Movies

Movies cannot be printed, but you can extract still images from movies, and print them after they have been saved. For details on how to save still images from movies, refer to [“Extracting Stills from Movies”](#).


- 1 Click the [Print & Email] task button in the Main Window.



- 2 Click [Photo Print].



- 3 Confirm that [1. Select Images] is chosen and select images for printing.




## 4

Click [2. Printer and Layout Settings] and set the categories as desired.

Sets the printer, paper size and borderless printing settings.

Click here to crop and print a portion of an image.

Click here to insert text onto an image and print.



Sets the shooting date/time imprint settings.

## 5

Click [3. Print].

Printing will start.

 **HINT****Printing Using Other Software**


If you have specialized printing software installed on the computer, you can also use it to print the images. Click the [Print & Email] task button in the Main Window, followed by [Print Using Other Software].

## Index Print


Prints an index of the images.




- 1 Click the [Print & Email] task button in the Main Window.



- 2 Click [Index Print].



- 3 Confirm that [1. Select Images] is chosen and select images for printing.



## 4 Click [2. Printer and Layout Settings] and set the categories as desired.

Sets the printer and paper size settings.

Rotates selected images.

Select an image to rotate or trim.

Click here to crop a portion of the selected image and print it.

Sets the number of rows or columns.

Configures the printing of the shooting information, comments, headers, footers or page numbers.

## 5 Click [3. Print]. Printing will start.


# How to Use CameraWindow

## First Menu Screen to Open

This screen appears when the camera is connected to your computer. Click each button to display the available options.

Displays in-camera memory card information.

Displays camera information.



Starts operations for transferring images from the camera to your computer.


Starts operations for protecting, rotating, and deleting images on the camera. Also transfers images from your computer to the camera.

Starts operations for uploading movies on the camera to web services.


Starts operations for setting the camera start-up screen, start-up sound, and various camera sounds. For details, refer to ["My Camera Settings"](#) in ["More Advanced Techniques"](#). This menu may not appear depending on your camera model.

### HINT

#### Customizing CameraWindow Functions

If you click the  button as shown in the upper right of the screen, you can customize various functions to make CameraWindow easier to use. You can change the automatic transfer settings, the start-up screen that appears when starting CameraWindow, and the transfer destination folder.

## Image Transfer Screen


This screen appears when you click [Import Images from Camera] on the Menu screen, then click [Select Images to Import]. Select the image you want to transfer and click the  button to transfer the image to your computer.

### Viewer Window (Thumbnail Display)


Returns to the Menu screen.



Images on the camera that match the selected filter display in the area to the right.


  Rotates chosen images 90° to the left or right.

The background of chosen images turns blue.

 Turns the shooting date and folder name below the thumbnails on and off (when in thumbnail display).

 Changes thumbnail size (when in thumbnail display).

 Closes CameraWindow.

 Switches between window display modes.


 Thumbnail display

 Preview display

 Full screen display

Double-clicking an image switches to preview display.

This mark appears on images that have not yet been transferred.

 Transfers the image chosen in Viewer Window to your computer.

 Cancels image selection.

 Selects all images.

### ! IMPORTANT


- The functions (buttons) that display will differ depending on the camera model.

## Organize Images Screen

This screen appears when you click [Organize Images on Camera] on the Menu screen, then click [Organize Images]. Clicking a folder on the left will display all images within the folder as thumbnails (small images) on the right of the screen.

### Viewer Window (Thumbnail Display)

Returns to the Menu screen.



Images on the camera that match the selected filter display in the area to the right.

Rotates chosen images 90° to the left or right.

The background of chosen images turns blue.

Turns the shooting date and folder name below the thumbnails on and off (when in thumbnail display).

Changes thumbnail size (when in thumbnail display).

Closes CameraWindow.

Switches between window display modes.

Thumbnail display

Preview display

Full screen display

Double-clicking an image switches to preview display.


This mark appears on images that have not yet been transferred.

Deletes the image chosen in Viewer Window.

Protects/cancels protection for the image chosen in Viewer Window.

Transfers images on your computer to the camera.

### ! IMPORTANT

- The functions (buttons) that display will differ depending on the camera model.
- Clicking the  (Delete) button will delete the image from the camera. Exercise adequate caution, as you cannot retrieve the deleted images.

# How to Use ZoomBrowser EX's Main Window

## Main Window

This is the main window for performing tasks in ZoomBrowser EX.

### Slide Show

Displays the selected images in succession in the window.

### Properties

Displays information about a selected image.

### View Image

Displays the selected image in the Viewer Window.

### Task Buttons

Selects a task to perform.

### Last Acquired Images

You can check images by shooting date or My Category.

### Search

Performs searches on images.

### Delete


Deletes the selected images or folders.

- Deleted images are sent to the Recycle Bin on the desktop.
- The association between a sound memo and an image cannot be recovered from a file restored from the Recycle Bin.

### Rotate

Rotates a selected image.

- Click the [Edit] menu and select [Rotate According to Rotation Information] to rotate the original image as well in the displayed direction.



### Display Mode

Selects a display mode for the Browser Area.

### Display Control Panel

Configures the settings for displaying images in the Browser Area.

### Browser Area

Displays the images in an index list.


### Folder Area

Selects a folder to display.

- You can register folders you use often as Favorite Folders ( ). Register by clicking [Add]. To delete a folder in the Favorite Folders area, select a folder and click the [Remove] button.

## Display Modes


Select a browser area display mode to fit your purposes.



**Zoom Mode:** suited for surveying many images.



**Scroll Mode:** allows thumbnails to be viewed at a size suited for easy viewing.




**Preview Mode:** allows the image information to be read while viewing the image.



### HINT

#### Magnify Thumbnails to Check Images

In zoom mode or scroll mode, positioning the mouse pointer over a thumbnail causes the image to appear at a higher magnification in a Mouse Over window. You can also set the Mouse Over window to not show in the  (Show Information) menu.

## Display Control Panel

This panel adjusts the display settings for the Browser Area.

#### Selection Menu

Click this to select/deselect all images in the Browser Area.

#### Select Button

Use this to select images in Zoom mode.

#### Fit to Window

Changes the thumbnail size to fit them into the window.

#### Display Size

Changes the size of the thumbnail in the Browser Area.

#### Show/Hide Image Information Menu

Select here to show/hide such image information as the file name or shooting date or rating beneath the thumbnail.

#### Zoom Button

Use this to zoom in and out on an image.

#### Scroll Button

Use this when in zoom mode to move the displayed portion of the image (drag inside the browser area).

#### Filter Tool Menu




Displays only images that correspond to specific conditions.



## Browser Area Tasks


### Change the Folder Level

The level of folder displayed can be changed with the following procedures.

- In Zoom mode, position the mouse cursor over the folder and click the  icon when it displays.
- In Scroll or Preview mode, double-click the  icon.
- To advance to a higher folder level, click the  icon.

### Change the Display Size


You can change the display ratio (Zoom mode) or thumbnail size (Scroll mode) with the slider.



### Select Images

Clicking an image in the Browser Area selects that image. To select multiple images, hold down the [Ctrl] key while clicking images, or hold down the [Shift] key and click a starting and ending image to select a range of adjacent images.

### Display Images

Double-clicking an image in the Browser Area (or selecting the image and clicking  (View Image)), displays it in the Viewer Window.

### Move, Copy Images

To move an image between folders, drag it over the destination folder and release the mouse button.

To copy an image, hold the [Ctrl] key while releasing the mouse button as above.

You can also use the same procedures to copy images between Windows Explorer and the Main Window.

### Create New Folder


To create a new folder in the Browser Area, click the [File] menu and select [New Folder].

## HINT

### Right-Click Context Menus

Right-clicking over a window or image displays contextual menus. These menus contain the functions available in the current context as well as other convenient functions. Use the right-click menus to increase your efficiency.

### Using the Navigator

If you change the displayed zoom factor in Zoom Mode, a Navigator Window that shows the current position will appear. In the Navigator Window you can change the position by dragging  or clicking inside the window.

## Properties Window

The Properties Window displays when you select an image in the Browser Area and click the Properties button. The Properties Window does not display in the Preview Mode.

Shows or hides categories.

**File Name**  
The file name can be changed.

**Rating and My Category**  
Sets the rating for an image. An icon will display if a My Category is set (certain models only).

**Protect**  
Prevents an image from being overwritten or deleted.

**Comment**  
You can type a comment here.

**Keywords**  
Sets the keywords used in searches.

**Brightness Histogram**  
A graph of the highlights and shadows distribution in an image.

**Shooting Information**  
Displays detailed information, such as the shutter speed and exposure compensation setting. The camera model will determine what information is displayed.

**Image Selector Buttons**  
When multiple images are selected, you can switch between images that display information in the Properties Window.

**Properties Window Details:**


- Modified:** 8/11/2009
- File Size:** 470.6 KB
- Image Size:** 1600 x 1200
- Data Type:** .JPG
- Sound:** [Play button]
- View Image...** [button]
- Protect** [checkbox]
- Path:** C:\Users\xxxx\Pictures\2009\_08\_11
- File Name:** IMG\_0001
- Rating and My Category:** [Rating stars: 3 yellow, 2 grey] [Category icon: flower]
- Comment:** Flower
- Keywords:** [empty field]
- Brightness Histogram:** [Graph showing distribution of highlights and shadows]
- Shooting Information:**

Item Name	Value
File Name	IMG_0001.JPG
Camera Model Name	Canon XXXX
Shooting Date/Time	8/11/2009 9:15:22 AM
Shooting Mode	Auto
Tv (Shutter Speed)	1/250
Av (Aperture Value)	7.1
Light Metering	Center Weighted Avg.
- Navigation:** < Previous, Next >

## Viewer Window

Double-clicking an image in the Main Window displays it in this window.

Change the display magnification.  
Zooming in displays the Navigator window to show the relative position on the image.




Edit an image.

Display the shooting information.  
You can configure the information display by clicking the [Tools] menu and selecting [Preferences].

Display at full screen size.

Set ratings.




Display multiple images side by side.

Shooting information

- The [Display Original Image] button will display beneath RAW images in the Viewer Window. Click this button to display the converted image in the Viewer Window.
- The following window will appear when a movie is displayed.

You can extract stills from movies.



You can cut portions at either end of a movie clip.

You can control movie playback and sound volume.

- A bar for changing the playback speed, and **1x** (real-time playback) will appear when a Super Slow Motion Movie is displayed. If you click **1x**, the movie will play back at the actual speed it was shot at.


# Editing Images

## ! IMPORTANT

- The original image will be overwritten after an image is edited unless the file name is changed before saving it. To preserve the original image intact, change the file name when saving the edited image.
- This section introduces the procedures started by clicking the Edit task button. Images can also be edited in a similar way by clicking the [Edit] button in the Viewer Window.

## Red Eye Correction

Restores eye appearance to the original color when light reflected from the flash makes them appear red.



- Click [Start] when Auto mode is selected.
- Switch to Manual mode if Auto mode cannot correct the image, and select the location of the eye to correct.

### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Image].
- 2 Select an image.
- 3 [2. Select Editing Tool]
- 4 [Red Eye Correction]
- 5 [3. Finish]

- Movies and RAW images cannot be edited.

## Auto Adjustment

Automatically adjusts the image color balance and brightness.




### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Image].
- 2 Select an image.
- 3 [2. Select Editing Tool]
- 4 [Auto Adjustment]
- 5 [3. Finish]

- Movies and RAW images cannot be edited.

## Color/Brightness Adjustment

You can adjust image color balance and brightness using a variety of methods.




### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Image].
- 2 Select an image.
- 3 [2. Select Editing Tool]
- 4 [Color/Brightness Adjustment]
- 5 [3. Finish]

- Movies and RAW images cannot be edited.

## Adjusting Sharpness—Emphasizing Outlines

Makes images appear sharper by emphasizing the outlines of subjects, such as people and objects.




### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Image].
- 2 Select an image.
- 3 [2. Select Editing Tool]
- 4 [Sharpness]
- 5 [3. Finish]

- The Unsharp Mask [Radius] is the size at which the outline is detected and the [Threshold] is the standard value at which the outline is determined.
- Movies and RAW images cannot be edited.

## Trimming–Cropping a Portion of an Image

Use this to delete unnecessary portions of the image and leave only the necessary portions.



### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Image].
- 2 Select an image.
- 3 [2. Select Editing Tool]
- 4 [Trim]
- 5 [3. Finish]

- You can also input values or an aspect ratio to specify the trim area.
- Movies and RAW images cannot be edited.

## Inserting Text

Use this to insert text onto the image.



### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Image].
- 2 Select an image.
- 3 [2. Select Editing Tool]
- 4 [Insert Text]
- 5 [3. Finish]

- Placing a checkmark in the [Antialias] box causes the text edges to blend in with the underlying image.
- Movies and RAW images cannot be edited.

## Using Other Editing Software

If you register another image editing program with ZoomBrowser EX in advance, you can use that software to edit an image selected in ZoomBrowser EX.

### Registering an Editing Program

Register the program so it can be started from within ZoomBrowser EX.



**ZoomBrowser EX**

**Other Image Editing Program**



#### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Image].
- 2 Select an image.
- 3 [2. Select Editing Tool]
- 4 [Edit with external image editor]
- 5 [Manage List]

### Editing Images with a Registered Editing Program




#### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Image].
  - 2 Select an image.
  - 3 [2. Select Editing Tool]
  - 4 [Edit with external image editor]
  - 5 [3. Finish]
- The shooting information may be lost from images recorded with the camera and then processed and saved with another image editing program.
  - Movies and RAW images cannot be edited.

## Attaching Sounds

You can add sound effects or background music to images and play back the sounds.


### Adding Sound



#### Procedures

1 Select an image.

2



**[Edit] and [Add/Remove Sound].**

- WAVE type sound files (extension ".wav") can be attached to images.
- Attaching a sound file to an image results in the selected sound file being copied into the same folder as the image file.


### Playing an Image Sound File



#### Procedures

1 Select an image.

2



**[Edit] and [Play Sound].**

## Creating Panoramic Images–PhotoStitch

You can create wide panoramic images by moving the camera slightly when recording a series of images and merging them into one image.



Use the PhotoStitch program to create panoramic images.



### Procedures

1 Select a task from the left side of the window: [Edit] and [Stitch Photos].

- Movies and RAW images cannot be edited.

### HINT

#### Using the Stitch Assist Mode


If you use the camera's Stitch Assist mode to record the images, PhotoStitch can automatically detect the image order and merge direction, making it easier to merge the images. (Some camera models may not feature the Stitch Assist mode.)

### ! IMPORTANT

- If a message appears, notifying you that the computer has insufficient memory, try one of the following methods to solve the problem.
  - Close all other applications other than PhotoStitch.
  - Reduce the size or number of images to combine.
  - In the [Save] tab, select [Adjust image...], then in "Saved Image Size" reduce the size.

## Editing Movies

You can create original movies by linking movie clips and still images. You can even add titles and other text, background music and various special effects to the movie.



### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Edit Movie].

### HINT

#### Recordable Movie Length

- The length of movies you can save is shown at right. A message will appear if you try to save a longer movie. Reduce the length or size of the movie if this happens.

#### Changing the Playback Speed of a Super Slow Motion Movie and Saving it as a New File

- Click [Slow Play Speed] in step 2 to change the playback speed (only with Super Slow Motion Movies).

Movie Size	Max. Length
1920x1080	Under 10 minutes
1280x720	Under 20 minutes
640x480	Under 30 minutes
320x240	Under 60 minutes


### IMPORTANT

- Movies edited with this function cannot be transferred back to the camera.
- Saving movies takes time, especially MOV type movies selected with [Save image type] takes a considerable amount of time.

## Converting RAW Images–Digital Photo Professional


You can convert RAW images to JPEG and TIFF images.

### Digital Photo Professional's Main Window



Selects folders containing images.

### Digital Photo Professional's Tool Palette




You can adjust all three RGB channel levels together or separately with the Tone Curve.

Reduces noise that occurs when shooting night time scenery, or when shooting at a high ISO speed.

Adjusts the brightness, white balance and picture style.

Adjusts attributes such as the contrast, color tone and color saturation.

### Procedures

- 1 Select a task from the left side of the window: [Edit] and [Digital Photo Professional Process RAW Images].
- 2 Select a RAW image in Digital Photo Professional's Main Window.
- 3 Click  (Edit image window).
- 4 Adjust the image brightness and white balance in the tool palette.
  - The modified contents (the information for image processing requirements) are saved along with the image as a "recipe".
  - With Digital Photo Professional, you can adjust images to achieve the best results for your desired scene or subject by specifying a picture style.
  - The items available to be modified differ depending on the camera model.
- 5 [File] and [Convert and save].
  - After setting the file type, size, and destination folder, click [Save].

- Only RAW images compatible with Digital Photo Professional can be processed.
- Ensure that you use the RAW image conversion software included with your camera.

To print, using Digital Photo Professional, select an image in the Main Window, then click the [File] menu and select the print function. Digital Photo Professional offers the following printing methods.

Printing Method	Description
<b>Single Print</b>	Automatically sets the layout for printing a single image on a single page.
<b>Detailed Setting</b>	Gives you the freedom to set the layout, add titles, or print with shooting information.
<b>Contact Sheet</b>	Prints a line-up of multiple images on one page (also allows you to select the number of images, layout, and add titles).


### ! IMPORTANT

- RAW images can only be captured on certain camera models that list "RAW" as one of the data types included in the "Specifications" section of the *Camera User Guide*.
- Only RAW images compatible with Digital Photo Professional can be processed. Check the "Data Type" item of the "Specifications" section of the *Camera User Guide* for compatibility.
- For a more detailed explanation of operating procedures, download the Digital Photo Professional manual (PDF format) from the Canon website.

### HINT

#### About RAW Images


RAW images contain the data captured by the camera's image sensor without modification. Since they contain raw data that differs from the usual JPEG images by not having any image adjustment or compression processing performed in the camera, they can be converted on a computer with a lossless process.



# Exporting

## Changing Image (Stills) Sizes and Types

You can change an image's size and format when exporting it so that it can be published on the Internet or attached to an email message.



### Procedures

1 Select a task from the left side of the window: [Export] and [Export Still Images].

- You will lose the shooting information if you save images as a type other than JPEG.

## Changing Movie Sizes and Types

You can change a movie's size and format when exporting it so that it can be published on the Internet or attached to an email message.



### Procedures

1 Select a task from the left side of the window: [Export] and [Export Movies].

- You can also use this function to rotate movies.




### IMPORTANT

- Exporting movies may take a considerable amount of time.

## Extracting Stills from Movies

You can extract and save stills from your favorite frames recorded in a movie.




# Procedures

- 1 Select a task from the left side of the window: **[Export]** and **[Extract frames from a movie]**.

## Exporting Shooting Information

You can export the shooting information recorded with an image, such as the shutter speed and exposure, as a text file.



### Ascertain the causes of failed photos or compare the settings for several images.



# Procedures

- 7 Select a task from the left side of the window: [Export] and [Export Shooting Properties].

## Creating Computer Screen Saver Images

You can export images to serve as computer screen savers.



### Procedures

- 1 Select a task from the left side of the window: [Export] and [Export as a Screen Saver].

## Creating Computer Wallpaper Images

You can export images to serve as computer wallpaper images.



### Procedures

- 1 Select a task from the left side of the window: [Export] and [Export as a Wallpaper].

## Saving to CDs


You can save images along with their shooting information to CD-R/RW discs.




### Procedures

- 1 Select a task from the left side of the window: [Export] and [Backup to CD].

### ! IMPORTANT


- This function can only be used with computers that satisfy the following requirements:
  - Equipped with a CD-R/RW drive as standard equipment
  - Writing to the CD-R/RW drive operates correctly with Windows
- If a window similar to that shown to the right appears when a new CD-R/RW disc is placed in the drive, click  ([Cancel] when using Windows XP) to close the window.





# Uploading Movies to YouTube

## Uploading to YouTube

You can upload movies you have shot to YouTube. You can upload movies saved on the camera or a computer.




### Procedures

- 1 Connect the camera to a computer to start CameraWindow.**
  - For details, refer to steps 1- 3 in ["Transferring Images"](#).
- 2 [Upload Images from Camera]**
- 3 [Upload Movies to YouTube]**
- 4 Select movies.**
- 5 Click  (Next).**
- 6 Input a title and description, then click  (Upload).**
- 7 Enter your YouTube username and password, and sign in.**

### HINT

#### Uploading Movies Saved on a Computer

Click the [Start] menu at the bottom left of the screen and select [All Programs] or [Programs] followed by [Canon Utilities], [CameraWindow], [Movie Uploader for YouTube] and [Movie Uploader for YouTube]. Click [Add] in the screen that appears, then after adding movies to the upload list, click the  (Upload) button.

### IMPORTANT

- Depending on YouTube specifications, or future changes to specifications, this function cannot be guaranteed.
- The maximum length for uploadable movies is less than 10 minutes, and the maximum file size is less than 1 GB.
- Movies that have been edited on a computer cannot be uploaded.
- Internet access is required to upload movies (You must already have an account with an Internet service provider (ISP), browser software installed and an Internet connection).
- Any ISP account charges and access fees must be paid separately.


# Email

## Attaching Images to Email

You can send images as email file attachments.

Click here for most images.

Click here when you want to change the image size or image quality settings, then click [Custom Settings] to change settings.



Click here to check the options currently set.

Click here to preview the compressed image.

Click here to check what the actual compressed file size will be.



### Procedures

- 1 **Select a task from the left side of the window: [Print & Email] and [Email Images].**
- 2 **Select an image to send.**
  - You can also select multiple images or all images in a folder.
- 3 **Click [2. Change Image Size]**
  - You can change the image size and quality settings.
- 4 **Click [3. Finish]**
  - The mail software will start, and the send screen will appear. The selected image will appear as an attached file.
  - In [Custom Settings], if [Save to Folder] is selected in "After Finishing the Task", the selected images will be saved in the indicated destination folder.



### HINT

#### Automatic Start-up Settings for E-mail Software

- When using Windows 7, you must pre-install an e-mail program. When changing settings, set the default program by clicking the [Start] menu, followed by [Default Programs].
- When using Windows Vista, configure the settings in your e-mail software. For example, you can configure Windows e-mail by starting e-mail, then clicking the [Tools] menu, followed by [Options], [Default Messaging Programs], [This application is not the default Mail handler], and [Make Default].
- When using Windows XP, settings can be configured by starting the Internet Explorer program, and clicking the [Tools] menu, followed by [Internet Options], [Programs] tab, and the [E-mail] pull-down menu.

### IMPORTANT

- The e-mail's MAPI client must be preset for the e-mail software to start automatically.
- If the e-mail software does not start automatically, first save the images to your computer, then start your e-mail software to attach and send the images. The destination folder for saved images can be set with [Custom Settings].



# Slide Shows

## Viewing Images in Slide Shows

A multiple selection of images can be shown at full size on the screen in succession as a slide show.

You can freely configure the transition effects, information displayed and display time settings.



### Procedures

- 1 Select a task from the left side of the window: [View & Classify] and [View as a Slide Show].

### HINT

#### Slide Show Button Functions

The following buttons appear at the bottom of the screen while a slide show is playing.

You can set the Rating for an image while it is displayed.

Rewind

Pause

Forward



After the slide show, the images you clicked during the show remain selected.


After the slide show, the images you clicked during the show appear in a printing window.

Stops the slide show.

# Image Management

## Changing File Names in Batches

You can change the file names of multiple images in one procedure.




### Procedures

- 1 Select a task from the left side of the window: **[View & Classify]** and **[Rename Multiple Files]**.

- You can change individual file and folder names by clicking the [File] menu and selecting [Rename] or by clicking on the file name in Preview mode.
- Changing the image name in ZoomBrowser EX also changes the actual file name on the disk.

## Sorting Images into Folders by Shooting Date

You can sort images into folders by their shooting dates.



### Procedures

- 1 Select a task from the left side of the window: **[View & Classify]** and **[Classify into Folder]**.

# Configuring Image Information Settings

## Setting Ratings

There are seven rating levels for images: ★, ★★, ★★★, ★★★★, ★★★★★, Unrated and Reject. By using ratings, you can group your images for viewing or searching.



### Procedures

1

Zoom Mode Scroll Mode **Preview Mode**

**Switch to [Preview Mode].**

2

**Set [Rating].**

- Ratings can also be set with the following:
  - ZoomBrowser EX's [Edit] menu or Properties Window, or the rating setting function of the Viewer Window.
  - The camera's [Tag as Favorite] function.
  - Windows 7/Windows Vista's [Rating] function (excluding movies).
- If you overwrite your previous installation when installing the software, existing rating settings may change. Refer to the Help function for details.

### ! IMPORTANT

- The only cameras that can be used to rate images will list "Favorites" in the "Menus" section of the "Playback Menu" table at the end of the *Camera User Guide*.

## Inserting Comments

You can freely insert your choice of text as Comments.



### Procedures

1

Zoom Mode Scroll Mode **Preview Mode**

**Switch to [Preview Mode].**

2

**Insert [Comment].**

- Comments can also be managed in the Properties Window.

## Assigning Keywords

You can set Keywords for use in image searches.



### Procedures

1 Zoom Mode Scroll Mode **Preview Mode**

**Switch to [Preview Mode].**

2 **Insert [Keywords].**

- Keywords can also be managed from the [Tools] menu or Properties Window.
- To add keywords, click the [Tools] menu and select [Manage Keywords].

### HINT

#### About Image Information

This chart shows the information other than shooting information that can be added to images.

Information Type	My Category	Ratings	Comments	Keywords
<b>Content</b>	Categories such as People, Scenery, etc.	Favorite images are rated by adding stars (★).	Text input without restriction regarding the shooting circumstances or associated memories.	Selections are made from a list (editable) of keywords, such as the photographic subject, place or action.
<b>Configuration Method</b>	Camera	ZoomBrowser EX, Digital Photo Professional, Camera (Favorite), Windows 7/Windows Vista (Rating)	ZoomBrowser EX	
<b>Used in Searches</b>	—	○	○	○
<b>Used as Filter Criteria</b>	○	○	—	—
<b>Display beneath Thumbnail</b>	○	○	○	—

Categories displayed beneath thumbnails can be selected by clicking  in the Display Control Panel.

# Searching, Filtering and Sorting Images

## Searching Images


You can search images using parameters extracted from the information associated with them.



### Procedures

- 1 Select a task from the left side of the window: [View & Classify] and [Search].

- After a search, the correlated images display in the [Search Results] folder.



### HINT

#### Tasks Related to Search Results

You can select images in the [Search Results] folder and perform operations on them, such as printing or copying them to other folders.

### IMPORTANT

- Please note that deleting an image from the [Search Results] folder deletes the original image. Use caution in deleting items from this folder.



## Filtering Images

You can use filters to display only images meeting the selected parameters in the Browser Area.




### Procedures

1

Filter


[Filter]



This section is used to specify the filter criteria.

## Sorting Images

You can sort images in the Browser Area based on the specified parameters.



### Procedures

1


ZoomBrowser EX - C:\Users\xxxx\Pictures  
File Edit **View** Tools Internet Help

[View] and [Sort by].







# Comparing Images

## Comparing Multiple Images


When a good photo opportunity arises, you can shoot the same subject using different shutter speeds and exposures. In ZoomBrowser EX, it is easy to compare images so that minute differences can be detected.



### Procedures

- 1 Select several images to compare.
- 2 Click  [View Image].
- 3 Select , ,  or  in the Viewer Window.
- 4 Click  [Synchronize].

- Selecting [Synchronize] causes actions such as increasing/reducing the magnification level or scrolling around the image to apply to all of the selected images in lock step, making it easy to check minute details of focus, coloring and other image characteristics.




Actions performed on an image, such as scrolling or changing the magnification, are performed on the other image as well.

# My Camera Settings

## Changing the Shutter Sound and Start-Up Image

You can select from dedicated screens to register to the start-up screen that appears when turning the camera on, and dedicated sounds to register to various camera operation sounds (My Camera Settings).




### Procedures

#### 1 Connect the camera to a computer to start CameraWindow.

- For details, refer to steps 1- 3 in ["Transferring Images"](#).

#### 2 [Camera Settings]



Select the desired item from the following and make settings.

- ▶ [Set Start-up Image]
- ▶ [Set Sounds]
- ▶ [Set Theme]


### ! IMPORTANT

- My Camera Settings are only available on certain models, when [Camera Settings] displays in CameraWindow.

My Camera Settings registered in the camera.

My Camera Settings

You can register the start-up image, start-up sound, shutter sound, operation sound and self-timer sound collectively if you select [Theme].



After choosing a My Camera Settings file from the left-hand list, select a My Camera Settings file to replace in the right-hand list and click this button to register it in the camera.

### HINT

#### Downloading My Camera Settings Files

You can also download various files to use in My Camera Settings from CANON iMAGE GATEWAY.


# Transferring Images

## Transferring Images to a Camera

Images transferred once to a computer can be transferred back to the camera.



### Procedures

- 1 **Connect the camera to a computer to start CameraWindow.**
    - For details, refer to steps 1- 3 in ["Transferring Images"](#).
  - 2 **[Organize Images on Camera]**
  - 3 **[Organize Images]**
  - 4  **(Upload)**
  - 5 **Select images.**
- If the Main Window is open when the camera is connected (directly after transferring for instance), open the CameraWindow (menu screen) by clicking the [Acquire & Camera Settings] task button, followed by [Connect to Camera].

### ! IMPORTANT

- Cameras that use the "MOV" data type can play back movies transferred back to the camera if movies were taken with that camera. Refer to the "Data Type" item in "Specifications" near the end of the Camera User Guide to see if the camera uses the "MOV" data type. You may not be able to play back movies taken with another camera.
- Only still images compliant with Design rule for Camera File system standards can be transferred to your camera's memory card.
- You may not be able to transfer images back to the camera if they have been edited on a computer, or if the image information has been modified.

# CANON iMAGE GATEWAY

## About CANON iMAGE GATEWAY (for U.S.A. customers only)

CANON iMAGE GATEWAY is an online photo service for the purchasers of this product. Registering online allows you to use the various services.

### ! IMPORTANT

- Internet access is required to use CANON iMAGE GATEWAY (You must already have an account with an Internet service provider (ISP), browser software installed and an Internet connection).
- See the homepage for information regarding browser versions (Microsoft Internet Explorer, etc.) and settings to best connect to CANON iMAGE GATEWAY online photo services.
- Any ISP account charges and access fees must be paid separately.

## Registering

First, register as a CANON iMAGE GATEWAY member.

Register



CANON  
**iMAGE**  
GATEWAY



### Procedures


- 1 Select [CANON iMAGE GATEWAY] from tasks on the left of the window, then select [Register/Add Product].

- You can register online using the supplied CD-ROM. To do this, in the installer panel, click [Register] underneath CANON iMAGE GATEWAY.



## Available Services


CANON iMAGE GATEWAY offers a variety of convenient and useful services.



# Preference Settings

## Customizing ZoomBrowser EX

You can configure ZoomBrowser EX and CameraWindow to your preferences.




- Overall themes, such as window appearances
- Processing methods for images shot with the camera on end
- Categories of shooting information displayed
- Show/hide messages
- Print settings
- Zoom speed



### Procedures

#### ZoomBrowser EX

1




[Tools] and [Preferences].

#### CameraWindow


1

Click  (Preferences).




## Customizing the Task Buttons

You can hide items that you do not usually use to streamline the task buttons.



### Procedures

1



[Tools] and [Customize].

# List of Available Functions

## CameraWindow Functions

Function Names		Description of Function
Import Images from Camera	<a href="#">Import Untransferred Images</a>	Only transfers images from the camera that have not yet been transferred.
	<a href="#">Select Images to Import</a>	Only transfers chosen images from the camera.
	<a href="#">Import All Images</a>	Transfers all images from the camera.
Organize Images on Camera	<a href="#">Organize Images</a>	Protect, rotate, and delete images on the camera. Also transfers images back to the camera from your computer.
Upload Images from Camera	<a href="#">Upload Movies to YouTube</a>	Uploads movies on the camera to YouTube.
Camera Settings	<a href="#">Set Start-up Image</a>	Sets the camera start-up screen.
	<a href="#">Set Sounds</a>	Sets camera sound effects (start-up sound, shutter sound, operation sounds, self-timer sound).
	<a href="#">Set Theme</a>	Sets the camera start-up screen and sound effects in My Camera Settings.
Preferences	<a href="#">General (General/Connected Camera)</a>	Sets the camera owner name, and start-up screen when CameraWindow starts.
	<a href="#">Import (Auto Import/Folder Settings/After Import)</a>	Sets the automatic transfer settings and destination folder.

## ZoomBrowser EX Functions

Task Button Names		Description of Function
Acquire & Camera Settings	<a href="#">Connect to Camera</a>	Connects to the camera to open CameraWindow (menu screen), and use CameraWindow functions.
	<a href="#">Acquire Images from Memory Card</a>	Transfers images from a memory card. You can also select images on the memory card and print them.
	<a href="#">Transfer Images to Memory Card</a>	Transfers images from the computer to a memory card.
View & Classify	<a href="#">View as a Slide Show</a>	Starts a slide show of the images selected in the Browser Area.
	<a href="#">Rename Multiple Files</a>	Changes the file names of the selected images in a single pass.
	<a href="#">Classify into Folder</a>	Classifies images and saves them into a specified folder.
	<a href="#">Search</a>	Performs image searches using criteria such as the Rating, modification date, shooting date, comments or keywords.

Task Button Names		Description of Function
Edit	Edit Image	Allows you to perform image editing, such as cropping, image correction, inserting comments, and red-eye correction. You can also use it to start other image editing programs.
	Stitch Photos	Merges multiple images and creates a single large panoramic image.
	Edit Movie	Edits movies or still images strung together. You can add text as titles, or background music, and apply various effects.
	Digital Photo Professional Process RAW Images	Converts RAW images into JPEG or TIFF images. You can adjust the image brightness, contrast and color balance among other attributes during conversion.
Export	Export Still Images	Allows you to change the image size or type, and export it as a new image.
	Export Movies	Allows you to change the movie size or type, and export it as a new movie.
	Extract frames from a movie	Extracts still images from movies over a specified interval and saves them as image files.
	Export Shooting Properties	Allows you to select the necessary data from the shooting information and export it as a text file.
	Export as a Screen Saver	Exports the image as a screen saver file.
	Export as a Wallpaper	Exports the image as a wallpaper file.
	Backup to CD	Copies images to a CD-R/RW disk for backup.
Print & Email	Photo Print	Prints one image per page. You can print “photos” easily.
	Index Print	Lines up small versions of the images in rows and prints.
	Print Using Other Software	Select the software to use and then print.
	Email Images	Converts the selected images to the appropriate size for transmission by e-mail. You can also use it to automatically start an e-mail program after conversion.
CANON iMAGE GATEWAY	Register/Add Product	Connects to CANON iMAGE GATEWAY and opens the registration page.
	Top Page	Connects to CANON iMAGE GATEWAY and goes to the top of the page.
	View Online Photo Album	Connects to CANON iMAGE GATEWAY and displays albums created.
	Upload Images	Connects to CANON iMAGE GATEWAY and uploads images.
	Download My Camera Contents	Connects to CANON iMAGE GATEWAY and downloads images and sounds for use with My Camera Settings.

## Supported Image Types

The following is a list of image types supported by ZoomBrowser EX.

### JPEG (.JPG)

Most cameras use this image type. It compresses at very high ratios, taking advantage of the characteristics of the human eye. However, because it is an irreversible compression method (part of the data is lost during compression), if you process and save an image repeatedly using this method, the image may become rougher.

### RAW (.CRW/.CR2)

This is a proprietary image type provided by Canon. It saves the output of the image pixels from a digital camera without any deterioration in the quality of the image. Some cameras might not support this image type.

### Windows bitmap (.BMP)

This image type comes standard with Windows. Most Windows programs support it.

### TIFF (.TIF)

This is a relatively popular image type. It is widely supported by non-Windows programs (such as Macintosh).

### PhotoCD (.PCD)

This is the image type used for Photo CDs.

### AVI (.AVI)

Standard Windows movie type. The movie icon appears in ZoomBrowser EX's Browser Area.

### MOV (.MOV)

Movie type. The movie icon appears in ZoomBrowser EX's Browser Area.

## Uninstalling the Software


The procedures for uninstalling the software are only required when you wish to delete the programs from your computer or when reinstallation is required to fix corrupted files.

### ! IMPORTANT

- Computer administrator status is required to perform the following operation.

This explanation uses ZoomBrowser EX to demonstrate how to uninstall a program. You can remove other programs with the same procedures.


- 1 Click the Windows [Start] menu and select [All Programs] or [Programs], followed by [Canon Utilities], [ZoomBrowser EX] and [ZoomBrowser EX Uninstall].



The uninstall utility will start and remove ZoomBrowser EX.

## Memory Card Folder Structure

Images on the memory card are in either the [DCIM] folder's [xxx\_\_mm] folder, or the [xxx\_mmdd] folder (xxx: numbers 100 to 999, mm: shooting month, dd: shooting day).



- \* These files are the thumbnail image files for the camera's index replay mode. If you delete these files, you will be unable to transfer movies to the camera from a computer.
- The "xxxx" in file names represent four-digit numbers.
- \*\* Each successive file shot in Stitch Assist mode is assigned a letter starting from "A," which is inserted as the third digit in the name. i.e. [STA\_0001.JPG], [STB\_0002.JPG], [STC\_0003.JPG]...
- All folders except the "xxx\_\_mm" or "xxx\_mmdd" folders contain image settings files. Do not open or delete them.
- Depending on the camera, some data types cannot be recorded.

# Troubleshooting

Please read this section if you encounter a problem using the software.

## Start by Checking This

Investigate the following points first if you encounter a problem.

### **Does your computer satisfy the requirements listed in the System Requirements section?**

See “System Requirements” in the *Camera User Guide*.

### **Is the camera correctly connected to the computer?**

See the *Camera User Guide* for the correct connection procedures. Also check to ensure that you are using the correct cable and that it is securely attached at both ends.

### **Are the camera and computer in the correct modes to transfer data?**

Some models require the camera to be set to the playback mode to transfer data. See the *Camera User Guide* for details.

### **Is the battery sufficiently charged?**

Check the battery charge if you are powering the camera with a battery. You are recommended to use an AC adapter (sold separately) to power the camera when it is connected to a computer.

## Problems

Try the suggested solutions to the common problems listed below.

### You can't find transferred images.

Refer to ["Changing the Transfer Destination Folder"](#) to confirm where the destination folder is.

### Add New Hardware Wizard displays when the camera is connected to the computer with an interface cable.

Click [Cancel] to close the window. Temporarily disconnect the camera from the computer. Next, read Start by Checking This on the previous page and resolve the problem.

### Camera not detected, Events dialog/AutoPlay/Device Stage won't display or images will not transfer to the computer (when camera is connected to the computer via an interface cable).

The camera may have been recognized as another device.

#### Solution:

Delete the device with the following procedures.

#### **IMPORTANT**

- Computer administrator status is required to perform the following operation.

#### 1 Display the [Device Manager] dialog.

##### Windows 7:

Click the [Start] menu, [Control Panel], [System and Security], [System], and [Device Manager].

##### Windows Vista:


Click the [Start] menu, [Control Panel], [System and Maintenance], [System], and [Device Manager].

##### Windows XP:

Click the [Start] menu, [Control Panel], [Performance and Maintenance], [System], [Hardware] tab, and the [Device Manager] button.

**2 Click the [+] symbol beside the [Other devices], [Portable Devices] and/or [Imaging devices] category.**

Your camera model name or [Canon Camera] will display in these categories if it is being recognized as an "other" device.



There are other potential reasons for the problem if the [Other devices], [Portable Devices] or [Imaging devices] categories do not appear or your camera model name or [Canon Camera] does not appear. Proceed to Step 5, and temporarily quit the procedures.

**3 Select your camera model name or [Canon Camera], right-click and select [Delete].**

**4 Click [OK] in the confirmation dialog.**

Delete all instances of your camera model name or [Canon Camera] if it appears in one or more places in the [Other devices] or [Imaging devices] categories.

**5 Close [Device Manager] or [System Properties].**

## Software Guide   Windows (ZoomBrowser EX, CameraWindow, PhotoStitch)

### Disclaimer

- Reprinting, transmitting, or storing in a retrieval system any part of this guide without the permission of Canon is prohibited.
- Canon reserves the right to change the contents of this guide at any time without prior notice.
- Illustrations and screenshots in this guide may differ slightly from the actual products.
- The above items notwithstanding, Canon accepts no liability for damages due to mistaken operation of the products.

